

Pinwheels Stocking

Designed by Jackie Robinson

A Fat Quarter friendly project 😊

Paisley fabric
By Maywood Studio



Maywood
S T U D I O

6000 N. Cutter Cir.
4561 Maywood Ave

Portland, OR 97217
Vernon, CA 90058

800.433.0722
800.237.6620

503.284.4124
323.584.8820

Pinwheels Stocking

Designed by Jackie Robinson, Animas Quilts
830 Douglas Hill Road
Eureka, MT 59917
www.animas.com

Fabric

Yardage - All Fat Quarters

Ecrú 1 – 7856-R

Ecrú 2 – 7856-G

Red – 7859-R

Green – 2108-G

Cuff - 7860-R

Backing - 2108-R5

Lining – 7858-G and 7858-R

Cutting

Ecrú 1

Cut (46) 1-7/8" squares

Ecrú 2

Cut (46) 1-7/8" squares

Red

Cut (46) 1-7/8" squares

Green

Cut (46) 1-7/8" squares

Cuff

Cut (2) 5-1/2" x 16-1/2"

Cut (1) 1-1/2" x 5-1/2"

Backing

Cut (1) 13" x 21"

Lining

Cut from Two Fat Quarters
(2) 13" x 21"


Construction

An accurate 1/4" seam allowance is imperative. Take time to do a seam allowance check before beginning. Cut TWO pieces of fabric exactly 1-1/2" x 4". Stitch them together with a 1/4" seam. Press in either direction. At the midpoint along this unit, measure across. It should be 2-1/2". If not, adjust your seam and repeat until you are correct.


This stocking finishes 8" wide. The piecing, when accurate, will allow you to place the pattern on, nearly exactly. Should your piece be too small because of large seams you may either add a small strip along the edge OR trim the stocking pattern a wee bit to make it fit,

The Stocking shaped pattern is available full size as a separate download named Stocking Template.


1. Draw a diagonal line the back of all (46) Ecrú 1 & (46) Ecrú 2 pieces. Place each Ecrú 1 right sides together with a 1-7/8" square of Red. Position each Ecrú 2 right sides together with a 1-7/8" square of Green. Stitch an accurate 1/4" on each side of the drawn line.




2. Cut the Step 1 units apart on the drawn line. Press toward the Red or Green. They will measure 1-1/2" square from raw edge to raw edge.




3. Stitch the Step 2 triangle units into 4-patch blocks, as shown. Make (23) of each color. Be mindful of the direction of each pinwheel. They all need to be the same.




4. Use the Step 3 units to lay out the Stocking Front patchwork. Stitch it together, taking care to maintain accuracy. Alternate the seams. Press carefully – very flat. The narrow part should be 8-1/2" wide, raw edge to raw edge. The vertical measurement is 20-1/2" raw edge to raw edge.



5. Position the Stocking pattern on the patchwork and cut the shape.




6. Place the Stocking pattern upside down on the right side of the 13" x 21" Backing. Cut a Stocking back in mirror image to the front.



7. In the same manner cut (2) mirror image Stocking patterns from the (2) 13" x 21" Lining pieces.

8. Right sides together, stitch the Stocking front and back together, leaving open at the upper edge. Clip the seams to the stitching line carefully in the curved areas. Turn right side out and finger press.

9. Right sides together, stitch the Lining front and back together, except . . . along the long 'back' seam, stitch about 4" from the top. Leave 6" 'open' for turning later. Continue stitching around the heel, toe and back to the top. Leave this piece inside out.



10. Place the (2) Cuff pieces that measure 5-1/2" x 16-1/2" right sides together. Stitch across the bottom. Open it and place the side seams

together, right sides together. A 1/4" seam along the side will close the cuff. Finger press this seam open. Turn right side out. It will be a 16" tube with a facing. The upper edge will be open.

11. Slide the Step 10 cuff over the outside of the right side out stocking. Pin in place with the upper raw edges even.

12. Make a loop to hang the stocking from the 1-1/2" x 5-1/2" Cuff. Fold both long edges toward the center, then fold that in half and stitch along the edge. Make certain it is right side out when stitched.

13. Fold the Step 12 loop in half. Match the raw edges to the raw edges of the top of the Stocking and pin in place.

14. Gently stuff the Step 11 Stocking inside the wrong side out Lining. Match the upper raw edges, taking care to have the toe heading the same direction on both pieces. Pin. Stitch around the upper edge.

15. Carefully pull the Stocking through the 6" opening you left in the Lining. Close the Lining opening by folding the seams to the inside, matching the folds, and stitching very close to the folded seams.

16. Stuff the Lining into the stocking. Shape the Cuff so it folds over the top of the Stocking, exposing the loop.



17. Embellish the Stocking, Cuff, or both.

Enjoy.

Stocking Template 50% of actual size. Print or copy at 200% to get actual size.
A full size template is available as a separate download named Stocking Template.

