# Bendre TRIPLE DYED BALIS BALI TROPICAL COVE





# **CUTTING INSTRUCTIONS**

WOF = Width of fabric | HST = Half Square Triangle | \*Sew strips via short ands, then subcut as indicated in pattern


WOF = Width of tabric   HST = Half Square Triangle   *Sew strips via short ends, then subcut as indicated in pattern								
	PATHWAYS A 9253-07 Cream/Multi	1/2 YD	(3) 4" x WOF strips, subcut (24) 4" squares		н	PATHWAYS 9253-99 Multi	1/2 YD	(3) 4" x WOF strips, subcut (24) 4" squares
	PATHWAYS B 9253-10 Red/Violet	1/2 YD	(3) 4" x WOF strips, subcut (24) 4" squares		J	CANE LEAF 9255-12 Black/Multi	1/2 YD	(6) 2-1/4" x WOF strips, BINDING
	PATHWAYS C 9253-38 Orange	1/2 YD	(3) 4" x WOF strips, subcut (24) 4" squares		K	CANE LEAF 9255-22	1/3	(2) 4" x WOF strips,
	PATHWAYS D 9253-55 Indigo/Multi	1/2 YD	(3) 4" x WOF strips, subcut (24) 4" squares			Berry/Yellow  CANE LEAF	YD 	subcut (16) 4" squares (2) 4" x WOF strips,
	PATHWAYS E 9253-66 Purple	1/2 YD	(3) 4" x WOF strips, subcut (24) 4" squares		L	9255-33 Yellow/Multi	YD	subcut (16) 4" squares
	PATHWAYS F 9253-82 Turquoise/Berry	1/2 YD	(3) 4" x WOF strips, subcut (24) 4" squares		M	CANE LEAF 9255-44 Green	1/3 YD	(2) 4" x WOF strips, subcut (16) 4" squares
	PATHWAYS G 9253-84 Turquoise	1/2 YD	(3) 4" x WOF strips, subcut (24) 4" squares		N	CANE LEAF 9255-65 Purple/Turquoise	1/3 YD	(2) 4" x WOF strips, subcut (16) 4" squares


3.

### **UNIT ASSEMBLY: Refer to UNIT DIAGRAMS**

- 1. Draw diagonal line on the wrong side of all A, B, D, and E, and (8) each of C, F,G and H 4" squares.
- 2. Place (1) marked A 4" square right sides together with (1) G 4" square. Sew 1/4" on either side of diagonal line, then cut on drawn line. Press open and square to 3-1/2". Repeat to make (32) AG UNITS.
- 3. Repeat Step 2 to create all remaining  $\mathbf{UNITS}$ . Square all to 3-1/2", make number indicated.

#### **UNIT DIAGRAMS**






#### **BLOCK ASSEMBLY: Refer to BLOCK DIAGRAMS**

- 4. Sew the indicated HST UNITS together into rows, pressing seam allowances in the direction of arrows. Sew rows together to create BLOCK 1. Square to 12-1/2", make (8).
- 5. Sew the indicated HST UNITS together into rows, pressing seam allowances in the direction of arrows. Sew rows together to create BLOCK 2. Square to 12-1/2", make (8).

NOTE: For Steps 4 & 5 - be sure to refer to IMAGES BELOW for proper rotation of HST UNITS.



## QUILT ASSEMBLY: Refer to QUILT DIAGRAM for proper block placement and rotation.

6. Sew blocks together into rows, then sew rows together.

#### FINISHING:

Cut batting and backing 3" larger than top on all sides. Layer backing, batting and top together and baste or pin. When quilting is completed, trim excess batting and backing. Bind with J fabric.

> Note: If this Benartex pattern is included in a kit, any questions about the kit should be addressed to the vendor from whom you bought it. Share your finished quilt with the Benartex Community on social media by tagging #benartex or #benartexfabrics Also visit our Sewing Group on Facebook, **Create Inspire Delight**

# FLUTTER BY QUILT DIAGRAM 48" X 48"

